Mageia NetInstall

Orodje za namestitev distribucije Mageia s pomočjo oddaljenih skladišč



Besedilo in zaslonski posnetki so licencirani z CC BY-SA 3.0 <u>http://creativecommons.org/licenses/by-sa/3.0/</u>.

Ta navodila so bila ustvarjena s pomočjo orodja <u>Calenco CMS</u> [http://www.calenco.com], ki ga je razvila firma <u>NeoDoc</u> [http://www.neodoc.biz].

It was written by volunteers in their free time. Please contact the <u>Documentation Team</u> [https://wiki.mageia.org/en/Documentation_team], if you would like to help improve this manual.

Mageia NetInstall

Kazalo

Installing Mageia using a Tiny Boot Image	
1. Introduction	
1.1. NetInstall Media	. 1
1.2. Installation Stages	
2. Stage 1 (Pre-installation Stage)	. 2
2.1. Boot	. 2
2.2. Installation Method	. 3
2.3. Network Connection	. 6
2.4. Mirrors	. 8
3. Stage 2 (Installation Stage)	11
3.1. Izberite jezik namestitve	
3.2. Licenčna pogodba in opombe ob izdaji	13
3.3. Nastavitev naprav SCSI	
3.4. Namestitev ali nadgradnja	
3.5. Tipkovnica	
3.6. Partitioning	
3.7. Software	27
3.8. User Management	33
3.9. Graphical Configuration	
3.10. Bootloader	
3.11. Configuration Summary	
3.12. Locale	
3.13. Nastavite vaše storitve	
3.14. Izberite miško	
3.15. Nastavitve zvoka	
3.16. Stopnja varnosti	
3.17. Požarni zid	
3.18. Posodobitve	
3.19. Čestitke	
3.20. Odstrani Magejo	

Seznam slik

1.	BIOS Welcome Screen	. 2
	UEFI Welcome Screen	
	EFI System Partition	
	BIOS boot partition	

Installing Mageia using a Tiny Boot Image

1. Introduction

1.1. NetInstall Media

1.1.1. Description

These minimal ISO's contain:

- less than 100 MB and are convenient if bandwidth is too low to download a full DVD, or if you have a PC without a DVD drive or unable to boot from a USB stick.
- no more than that which is needed to a) start the DrakX installer and b) find DrakX-installer-stage2 and other packages that are needed to continue and complete the install.

The required source packages may be on a PC hard disk, a local drive, a local network or on the Internet.



Installation via encrypted wifi or bluetooth is not supported.

1.1.2. Availability

There a two versions of the NetInstall media:

- **netinstall.iso** For those who prefer not to use non-free software, this ISO contains only free software.
- **netinstall-nonfree.iso** This ISO additionally includes proprietary device drivers, which may be required for your network device, disk controller, etc.

Both versions are available in the form of separate 32-bit and 64-bit ISO's. See here: <u>https://www.mageia.org/downloads/</u>

1.1.3. Preparation

After downloading the image, burn it to a CD/DVD or, if you prefer to put it on a USB stick, follow the instructions here: <u>https://wiki.mageia.org/en/Installation_Media#Dump_Mageia_ISOs_on_an_USB_stick</u>

1.2. Installation Stages

The installation is carried out in two stages:

- **Stage 1** This is the pre-Installation stage. You will need to provide the method and details for accessing the medium containing the files to be used for the installation. If the method involves a server, then the network connection will be activated.
- **Stage 2** This is the actual Installation stage, which will automatically commence once a connection to the installer files has been established.



During Stage 1, nothing will be written to your Hard Disk, so it is safe to quit at any point during Stage 1 if you wish. You can do so by pressing **Ctrl+Al-t+Del**.



You can use **Alt+F3** to read the logs and **Alt+F1** to return to the installer screen.



Unlike when installing from DVD or LiveCD, during the first part of the installation (**Stage 1**), you will be asked to type things. During this stage, your keyboard will operate as per an <u>American keyboard</u> [https://en.wikipedia.org/wiki/Keyboard_layout#United_States] layout. This can be very confusing when you need to type names and paths.

2. Stage 1 (Pre-installation Stage)

2.1. Boot

The particular Welcome Screen that you will see when booting with the NetInstall media depends on whether you are booting on a BIOS or UEFI system. See the following two screenshots:

Welcome to Mageia install help In most cases, the best way to get started is to simply press the (Enter) key. If you experience problems with standard install, try one of the following install types (type the highlighted text and press (Enter)): o text for text installation instead of the graphical one. o linux for standard graphical installation at normal resolution. o linux vga=785 for low resolution graphical installation. To repair an already installed system type rescue followed by (Enter). You can also pass some (specific kernel options) to the Linux kernel. For example, try linux noapic if your system has trouble operating your network adapter correctly. NOTE: You cannot pass options. If you need to do so, use noauto mode. [F1-Help1 [F2-Advanced Help1] boot: _

Slika 1. BIOS Welcome Screen

When booting up, you can choose to read the advanced help by pressing **F2** and return to the installer screen by pressing **F1**. Otherwise, the boot will continue with default settings.



Slika 2. UEFI Welcome Screen

• Use the arrow keys to highlight Start Mageia Install and then press **Enter**.


For both BIOS and UEFI systems, you will then see a pop-up notification saying that USB devices are being detected:



2.2. Installation Method

You can now choose an installation method via CDROM/HDD or Server (NFS, FTP or HTTP).

You also have the option to load third-party modules at this point.



- Move up or down the list using the arrow keys until the appropriate method of installation is highlighted.
- Press the **Tab** key until Ok is highlighted and then press **Enter**.

2.2.1. Server

- If you don't know what to choose for a Network Installation, choose FTP server.
- On an enterprise network, FTP and rsync may be blocked, so using HTTP server is a good choice in this case.

After choosing any of the server options you will automatically proceed to the <u>Network</u> <u>Connection</u> section.

2.2.2. CDROM/HDD


If you choose to install from either a CDROM or hard disk (or USB stick), a scan for storage devices will be performed:



• First, select the relevant hard drive (or USB stick)



• Followed by the relevant partition



• Then specify the directory or the file name of the ISO

Leaving this open, or using the directory is easier, because the installer then presents you with a list of directories and files from which you can make your selection using the up and down arrows, as seen in the second of the following images.





Once the information has been provided for the location of the ISO, either on CDROM or HDD, you will automatically proceed to $\frac{\text{Stage 2}}{\text{Stage 2}}$ (the actual installation stage).

2.2.3. Load Third-Party Modules

If you wish to Load third-party modules, then you will be asked for the location of the directory containing the modules:



2.3. Network Connection


2.3.1. Connection Device

If you chose any of the server options at the Installation Method step, you will then be asked to choose a network device:



2.3.2. Connection Type

Now you need to choose whether the network device will use a DHCP, Static or ADSL connection:



If you are unsure which option is suitable, then you should probably accept the default option (DHCP).

2.3.3. Host/Domain Names

If necessary, you can now supply your Host and Domain names:



• If you are unsure what this means then you can just leave the fields blank, highlight Ok and press **Enter** to proceed. The network connection will now be activated.

If you are using either FTP or HTTP, you will automatically proceed to the Mirrors section

If you are using NFS, you will be asked for the NFS server name and the directory containing the Mageia distribution:

P	lease fill in entries	
	name or IP address of ye containing the Mageia 1	· · · · · · · · · · · · · · · · · · ·
NFS server name Mageia directory		
Ok	Ca	ncel

After entering the NFS details, you will automatically proceed to <u>Stage 2</u> (the actual installation stage).

2.4. Mirrors

If using FTP or HTTP, you now have to specify a mirror to use. This can be done manually or by choosing from a list



2.4.1. Specify Manually

You will find a list of all available mirrors here: http://mirrors.mageia.org/

Whichever mirror you choose, it should use the same tree-like structure from "mageia" (or "Mageia") as used by the official Mageia mirrors. That means .../mageia/distrib/<version>/<arch>

A correct entry (when using an official mirror) in the Mageia directory field below, could be:

pub/linux/mageia/distrib/cauldron/i586

Another example (for Mageia 6 x86_64) could be:

pub/Mirrors/Mageia/distrib/6/x86_64

Other mirrors may have a different path structure and the screenshots below show such examples:

If you are using an FTP server:

Please fill in entries
Please enter the name or IP address of the FTP server, the directory containing the Mageia Distribution, and the login/pass if necessary (leave login blank for anonymous).
FTP server ftp.belnet.be Mageia directory /mirror/mageia/distrib/6/x86 64
Login Password
Ok Cance 1

If you are using an HTTP server:



Once this information has been provided, you will automatically proceed to <u>Stage 2</u> (the actual installation stage).

2.4.2. Select From a List

V primeru, da se kasneje v namestitvi pojavi več napak z manjkajočimi odvisnostmi, ponovno zaženite računalnik ter ponovite namestitev, a z drugega zrcala.

Please choose
Please select a mirror from the list below.
Specify the mirror manually vodka.sublink.org ftp.twaren.net ftp.cc.uoc.gr ftp-stud.hs-esslingen.de ftp.belnet.be ftp.linux.org.tr
Ok Cance 1

After choosing an FTP server, you will see a screen where you can optionally add a login name and password if required.

Please fill in entries
Please enter the name or IP address of the FTP server, the directory containing the Mageia Distribution, and the login/pass if necessary (leave login blank for anonymous).
FTP server ftp.belnet.be
Mageia directory /mirror/mageia/distrib/6/x86_64
Login Password
Ok Cancel

Once this information has been provided, you will automatically proceed to <u>Stage 2</u> (the actual installation stage).

3. Stage 2 (Installation Stage)

Nothing has been written to your hard disk at this point. Therefore, if you decide not to proceed with the actual installation, then it is safe to reboot now: go to tty2 with **Ctrl+Alt+F2** and press **Ctrl+Alt+Del** (or **Ctrl+Alt+F7** to come back if you change your mind).

3.1. Izberite jezik namestitve

- Select your preferred language, by first expanding the list for your continent. Mageia will use this selection during the installation and for your installed system.
- If it is likely that you (or others) will require several languages to be installed on your system, then you should use the Multiple languages option to add them now. It will be difficult to add extra language support after installation.

Ömageja	PLEASE CHOOSE A LANG	UAGE TO USE	
INSTALLATION Language License Partitioning Installing CONFIGURATION Users Summary Updates Exit	 - -	Sardu Shqip Slovenčina Slovenščina Srpska Cpпска Suomi Svenska Türkçe Українська Walon Avañe'ё	Next



Even if you choose more than one language, you must first choose one as your preferred language from the main list of languages. It will also be marked as chosen in the Multiple languages screen.

- If your keyboard language is not the same as your preferred language, then it is advisable to install the required language for your keyboard as well
- Mageia uses UTF-8 (Unicode) support by default. This may be disabled in the Multiple languages screen if you know that it is inappropriate for your language. Disabling UTF-8 applies to all installed languages.
- You can change the language for your system post-installation in the Mageia Control Center → System → localization for your system.

3.2. Licenčna pogodba in opombe ob izdaji

Ömageia	LICENČNA POGODBA
NAMESTITEV Jezik • Licenca • Razdelitev diska • Nameščanje • NASTAVITEV Uporabniki • Povzetek • Posodobitve • Izhod •	 Ta prevod licence je na voljo samo v informacijo, uradna, pravno veljavna verzija je v angleščini. Predstavitev Operacijski sistem in razne komponente, ki so na voljo v distribuciji Mageia, se v nadaljevanju imenujejo »Programska oprema«. Programska oprema vključuje, vendar ni omejena na, nabor programov, metod, pravila in dokumentacijo v zvezi z operacijskim sistemom in različnimi komponentami distribucije Mageia, ter vse programe dodane tem izdelkom, ki jih razširja skupnost Mageia. 1. Licenčna pogodba Pazljivo preberite ta dokument. Ta dokument je licenčna pogodba med vami in skupnosti Magoja tor se papača na Programska oprema Z pamostibuja Ali sprejmete te licenčne pogoje? Sprejmem
6	Dopombe ob izdaji
	▶ Pomoč Izhod Naprej

3.2.1. Licenčna pogodba

- Before installing Mageia, please read the license terms and conditions carefully.
- These terms and conditions apply to the entire Mageia distribution and must be accepted before you can continue.
- To proceed, simply select Accept and then click on Next

If you decide not to accept these conditions, then we thank you for your interest in Mageia. Clicking Quit will reboot your computer.

3.2.2. Opombe ob izdaji

Important information about this particular Mageia release can be viewed by clicking on the Release Notes button.


3.3. Nastavitev naprav SCSI

۸	
Ömageia	ZAZNAVA TRDIH DISKOV
NAMESTITEV	Kateri disk/card_reader gonilnik naj poizkusim?
Jezik ● Licenca ●	3w_9xxx (3ware 9000 Storage Controller Linux Driver)
Razdelitev diska	3w_sas (LSI 3ware SAS/SATA-RAID Linux Driver)
Nameščanje •	3w_xxxx (3ware Storage Controller Linux Driver)
, in the second s	53c7,8xx
NASTAVITEV	AM53C974
Uporabniki 🔍	BusLogic
Povzetek 🔍	DAC960
Posodobitve 🄍	NCR53c406a
Izhod 🔍	a100u2w (Initio A100U2W SCSI driver)
	a320raid
	aacraid (Dell PERC2, 2/Si, 3/Si, 3/Di, Adaptec Advanced Raid Products, HP NetR
1	advansys
4	aec62xx (PCI driver module for ARTOP AEC62xx IDE)
<u> </u>	
<u></u> 💎	Nazaj Naprej
Ser -	

DrakX will normally detect hard disks correctly. However, with some older SCSI controllers it may be unable to determine the correct drivers to use and subsequently fail to recognise the drive.

If your device is not recognised, you will need to manually tell DrakX which SCSI drive(s) you have. DrakX should then be able to configure the drive(s) correctly.

3.4. Namestitev ali nadgradnja



• Install

Use this option to perform a fresh installation of Mageia. This will format the root partition (/), but can preserve a pre-existing /home partition (a dedicated /home partition, rather than being incorporated within the root (/) partition itself).

• Upgrade

Use this option to upgrade an existing installation of Mageia.



Only upgrading from a previous Mageia version that was still supported when this Installer's version was released, has been thoroughly tested. If you want to upgrade a Mageia version that has reached its "End Of Life" then it is better to do a "clean" install instead, while preserving your /home partition.



If you have discovered that you forgot to select an additional language, you can return from the Install or Upgrade screen to the language choice screen by pressing **Ctrl+Alt+Home**. Do **NOT** do this later in the install.

3.5. Tipkovnica

DrakX selects an appropriate keyboard for your language. If no suitable keyboard is found it will default to a US keyboard layout.

Ömageia	ΤΙΡΚΟΥΝΙCA	
NAMESTITEV Jezik ● Licenca ● Razdelitev diska ● Nameščanje ● NASTAVITEV Uporabniki ● Povzetek ●	Izberite razpored tipkovnice Ameriška (mednarodna) Angleška (ZDA) Angleška (Združeno kraljestvo) Dvorakova (Združeno kraljestvo) Hrvaška Slovenska	
Posodobitve • Izhod •	▶ Več	Naprej

- Make sure that the selection is correct or choose another keyboard layout. If you don't know which layout your keyboard has, look in the specifications that came with your system, or ask the computer vendor. There may even be a label on the keyboard that identifies the layout. You can also look here: <u>en.wikipedia.org/wiki/Keyboard_layout</u> [http://en.wikipedia.org/wiki/Keyboard_layout]
- If your keyboard isn't in the list shown, click on More to get a fuller list, and select your keyboard there.



After choosing a keyboard from the More dialogue, you'll return to the first keyboard choice dialogue and it will seem as though a keyboard from that screen was chosen. You can safely ignore this and continue the installation: the keyboard chosen from the full list will be applied.

 If you choose a keyboard based on non-Latin characters, you will see an extra dialogue screen asking how you would prefer to switch between the Latin and non-Latin keyboard layouts

3.6. Partitioning

3.6.1. Suggested Partitioning

In this screen you can see the content of your hard drive(s) along with the DrakX partitioning proposals for where to install Mageia. The actual options available from those shown below will vary according to the layout and content of your particular hard drive(s).

Ö mageja	RAZDELITEV DISKA
NAMESTITEV Jezik @ Licenca @ Razdelitev diska Nameščanje NASTAVITEV Uporabniki Povzetek Posodobitve Izhod	To je vsebina trdega diska Fujitsu MHZ2320B (298GB) SYSTEM_DRV Windows7_OS Carovnik za razdeljevanje diska je našel naslednje rešitve: Uporabi obstoječe razdelke Uporabi razpoložljivi prostor SYSTEM_DRV Windows7_OS Uporabi razpoložljivi prostor v razdelku za Windows SYSTEM_DRV Windows7_OS Windows (73GB) Mageia (24GB) Zbriši in uporabi celoten disk Razdeljevanje diska po meri
	▶ Pomoč

Main Options

• Use Existing Partitions

If this option is available, then existing Linux compatible partitions have been found and may be used for the installation.

• Use Free Space

If you have unused space on your hard drive then this option will use it for your new Mageia installation.

• Use Free Space on a Windows Partition

If you have unused space on an existing Windows partition, the installer may offer to use it. This can be a useful way of making room for your new Mageia installation, but is a risky operation so you should make sure you have backed up all important files!

With this option, the installer displays the remaining Windows partition in light blue and the proposed Mageia partition in dark blue with their intended sizes just underneath. You have the option to modify these sizes by clicking and dragging the gap between both partitions. See the following screenshot:

Erase and use Entire Disk

This option will allocate the entire drive for Mageia



This will erase ALL data on the selected hard drive. Take care! If you intend to use part of the disk for something else, or you already have data on the drive that you are not prepared to lose, then do not use this option.

Note that this involves shrinking the size of the Windows partition. The partition must be "clean", meaning that Windows must have closed down correctly the last time it was used. It must also have been defragmented, although this is not a guarantee that all files in the partition have been moved out of the area that is about to be used. It is highly recommended to back up your personal files.

Custom Disk Partitioning

S tem imate popoln nadzor nad namestitvijo na (enem ali več) vaših diskov.

Ö mageia	
Mageia 5 INSTALLATION Language • License • Partitioning • Installing • CONFIGURATION Users • Summary • Updates • Exit •	PARTITIONING Here is the content of your disk drive Maxtor 6L160M0 (152GB) PARTITIONING Partitioning wizard found the following solutions: Partitioning Partitioning Partitioning Partitioning Partitioning Partitioning

If you are not using the Custom disk partitioning option, then the installer will allocate the available space according to the following rules:

- If the total available space is less than 50 GB, then only one partition is created. This will be the / (root) partition.
- Če je vsega razpoložljivega prostora na voljo več kot 50 GB, bodo ustvarjeni trije razdelki
 - 6/19 of the total available place is allocated to / with a maximum of 50 GB

- 1/19 is allocated to swap with a maximum of 4 GB
- the rest (at least 12/19) is allocated to /home

This means that from 160 GB or greater available space, the installer will create three partitions:

- 50 GB for /
- 4 GB for swap
- and the remainder for /home



If you are using a UEFI system, the ESP (EFI System Partition) will be automatically detected - or created if it does not exist yet - and mounted on / boot/EFI. The Custom disk partitioning option is the only one that allows to check it has been correctly done.

If you are using a Legacy (also known as BIOS) system with a GPT partitioned disk, you need to create a BIOS boot partition if it doesn't already exist. It should be about 1 MiB with no mount point. It can be created with the Installer, under Custom disk partitioning, like any other partition. Be sure to select "BIOS boot partition" for filesystem type.

See <u>DiskDrake</u> for information on how to proceed.

Omageia	PARTITIONING
Mageia 6 INSTALLATION Language • License • Partitioning • Installing • CONFIGURATION Users • Summary • Updates • Exit •	Click on a partition, choose a filesystem type then choose an action sda sdb , /, /me, ub, /r.o, / 20GB 18CB 20GB 25GB 25GB 25GB 25GB 25GB 25GB 25GB 26GB 26GB 20GB 20GB 20GB 20GB 20GB 20GB 20GB 20
	Clear all Auto allocate Toggle to expert mode Image: Help More Done

CHANGE PARTITION TYPE			
Which fil	esystem do you want?		
Туре	AIX		1
	AIX bootable		
	AST SmartSleep		
	Amoeba		
	Amoeba BBT		
	BBT		
	BIOS boot partition		
	BSD/OS		
	BSDI fs		
	BSDI swap		
	BeOS fs		
	Boot Wizard hidden		
	Bootit		
	CP/M		
	CP/M / CTOS /		
	Compaq diagnostics		
	DOS R/O		
		Cancel	Ok



Some newer drives are now using 4096 byte logical sectors, instead of the previous standard of 512. Due to lack of available hardware, the partitioning tool used in the installer has not been tested with such a drive.

Some SSD devices now use an erase block size over 1 MB. If you have such a device we suggest that you partition the drive in advance, using an alternative partitioning tool like gparted, and to use the following settings:

- Align to = MiB
- Free space preceding (MiB) = 2


Also make sure all partitions are created using an even number of megabytes.

3.6.2. Izberite priklopne točke

8		
Ömageia	RAZDELITEV DISKA	
	Izberite priklopne točke	
NAMESTITEV	sda5 (3GB, /, btrfs) /	-
Jezik ● Licenca ●	sda6 (11GB, ext4)	5
Razdelitev diska 🔍	sda8 (4.1GB, /home, ext4) /home 🗸 🗸	•
Nameščanje 🔍	sda9 (6.8GB, ext4)	•
NASTAVITEV	sda10 (1.3GB, ext4)	•
Uporabniki 🔍 Povzetek 🔍	sda12 (2.4GB, btrfs)	•
Posodobitve		
Izhod 🔍		
	~	
	▶ Pomoč Nazaj Naprej	

Here you see the Linux partitions that have been found on your computer. If you don't agree with the DrakX suggestions, you can change the mount points yourself.

- To the left of the drop-down menus is a list of available partitions. For example: sda is a hard drive and 5 is a partition number, followed by the (capacity, mount point, filesystem type) of the partition.
- If you have several partitions, you can choose various different mount points from the drop down menu, such as /, /home and /var. You can even make your own mount points, for instance /video for a partition where you want to store your films, or perhaps /Data for all your data files.
- For any partitions that you don't need to make use of, you can leave the mount point field blank.





If you are not sure what to choose, click Previous to go back and then tick Custom disk partitioning, where you can click on a partition to see its type and size. If you are sure the mount points are correct, click on Next, and choose whether you only want to format the partition suggested by DrakX, or more.

3.6.3.	Potrdi	formatiranje	trdega	diska
--------	--------	--------------	--------	-------

<u>, 8</u>	
Ömageia	RAZDELITEV DISKA
NAMESTITEV	VSI razdelki na disku sda (37GB, Toshiba MK4026GA) in podatki na njih bodo izgubljeni.
Jezik •	
Licenca ● Razdelitev diska ●	
Nameščanje 🔍	
NASTAVITEV Uporabniki	
Povzetek 🔍	
Posodobitve Izhod 	
6	₩
N	▶ Pomoč Nazaj Naprej

- Click on Previous if you are at all unsure about your choice.
- Click on Next to proceed if you are sure that it is OK to erase **every** partition, **every** operating system and **all data** that might be on that hard disk.

3.6.4. Custom Disk Partitioning with DiskDrake

Omageia	RAZDELITEV DISKA	
	Izberite razdelek, vrsto datotečnega sistema ir	dejanje
	sda sdb	
NAMESTITEV	/media/ / /ho	Prikaži
Jezik ● Licenca ●	5.9GB 3GB 2.4GB	Priklopna točka
Razdelitev diska 🔍	Ext4 XFS Swap Windows Drugo Prazno	Spremeni velikost
Nameščanje	Podrobnosti	Izbriši
NASTAVITEV	Priklopna točka: /home Naprava: sda12	
Uporabniki 🔍 Povzetek 🔍	Vrsta: Journalised FS: Btrfs Velikost: 2.4GB (6%)	
Posodobitve 🍳	I	
Izhod 🔍 🗌		
1	Zbriši vse	Razdeli samodejno
6		reklopi v napredni način
	(P	rekiopi v napredni način
N	▶ Pomoč	Več Opravljeno
20		

- Modify the layout of your disk(s) here. You can remove or create partitions, change the filesystem or size of a partition and even view their details before you start.
- There is a tab at the top for every detected hard disk (or other storage device, like a USB key). In the screenshot above there are two available devices: sda and sdb.
- For all other actions: click on the desired partition first. Then view it, or choose a filesystem and a mount point, resize it or wipe it. Expert mode provides more options such as to label (name) a partition, or to choose a partition type.
- Continue until you have adjusted everything to your satisfaction, then click Done when you're ready.

	Take care with the Clear all option, use it only if you are sure you want to wipe all partitions on the selected storage device.
2.	If you wish to use encryption on your / partition you must ensure that

2. If you wish to use encryption on your / partition you must ensure that you have a separate /boot partition. The encryption option for the /boot partition must NOT be set, otherwise your system will be unbootable.



- If you are installing Mageia on a UEFI system, check that an ESP (EFI System Partition) is present and correctly mounted on /boot/EFI. See Figure 1 below.
 - If you are installing Mageia on a Legacy/GPT system, check that a BIOS boot partition is present and of the correct type. See Figure 2 below.

X ⊙ Mageia Control Center [on localhost] ⊗ ⊗ ⊗ File Options Help
Manage disk partitions
Click on a partition, choose a filesystem type then choose an action
sda sdb sdc
/boot/EFI / A9GB 3.9GB /home 98GB
Ext4 XFS Swap Windows Other Empty
Details Device: sda Size: 152GB Name: Maxtor 6L160M0
Clear all
Toggle to expert mode
▶ Help

Slika 3. EFI System Partition

Ömageia	
Ornageia	PARTITIONING
Mageia 6	Click on a partition, choose a filesystem type then choose an action
	sda sdb
INSTALLATION Language • License •	/ /me ub /ho / Resize 20GB 18GB 20GB 25GB
Partitioning •	Delete
Installing	Ext4 XFS Swap Windows Other Empty
	Details
CONFIGURATION Users	Device: sda3 Type: BIOS boot partition
Summary	Size: 1MB (0% of disk) Not formatted
Updates •	Not formatted
Exit •	
and the second	Clear all Auto allocate Toggle to expert mode
	Help More Done

Slika 4. BIOS boot partition

3.6.5. Formatiranje

Ö mageia	FORMATIRANJE
NAMESTITEV Jezik • Licenca • Razdelitev diska • Nameščanje •	Izberite razdelke, ki jih želite formatirati ✔ sda2 (6.4GB, /, ext4) ▶ Napredno
NASTAVITEV Uporabniki • Povzetek • Posodobitve • Izhod •	•
	▶ Pomoč Nazaj Naprej

Here you can choose which partition(s) you wish to format. Any data on partitions not marked for formatting will be preserved.

Usually, at least the partitions that DrakX selected need to be formatted.

Click on Advanced to choose the partitions you want to check for so-called bad blocks



If you're not sure you have made the right choice, you can click on Previous, again on Previous and then on Custom to get back to the main screen, where you can choose to view details of your partitions.

When you are confident about the selections, click on Next to continue.

3.7. Software

3.7.1. Media Selection

3.7.1.1. Supplemental Installation Media

() mageia	IZBIRA VIROV	
NAMESTITEV Jezik • Licenca • Razdelitev diska • Nameščanje • NASTAVITEV	Zaznani so bili naslednji viri, ki bodo uporabljeni med namestitvijo: - Core Release, - Nonfree Release. Ali imate še kak dodaten namestitveni vir, ki ga je potrebno nastaviti?	
Uporabniki Povzetek	Brez	
Posodobitve ● Izhod ●	Brez CD-ROM	
	Omrežje (HTTP)	
	Omrežje (FTP)	
	Omrežje (NFS)	
~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~	▶ Pomoč	Naprej
48		

This screen shows you the list of already recognised repositories. You can add other sources for packages, like an optical-disc or a remote source. The source selection determines which packages will be available during the subsequent steps.

Za omrežni vir je potrebno slediti dvema korakoma:

- 1. Choosing and activating the network, if not already up.
- 2. Selecting a mirror or specifying a URL (very first entry). By selecting a mirror, you have access to the selection of all repositories managed by Mageia, like the Nonfree, the Tainted repositories and the Updates. With the URL, you can designate a specific repository or your own NFS installation.



If you are updating a 64-bit installation which may contain some 32-bit packages, it is advised to use this screen to add an online mirror by selecting one of the Network protocols here. The 64-bit DVD ISO only contains 64bit and noarch packages, it will not be able to update the 32-bit packages. However, after adding an online mirror, the installer will find the needed 32bit packages there.

#### 3.7.1.2. Available Media

Ömageja	
Ornageia	IZBIRA VIROV
NAMESTITEV Jezik ● Licenca ● Razdelitev diska Nameščanje NASTAVITEV	Tu lahko po želji omogočite več virov. Nekateri deli vaše strojne opreme za pravilno delovanje odprtokodnih gonilnikov potrebujejo lastniško strojno programsko opremo. Priporočljivo je omogočiti vir »Lastniški (nonfree) - izdajni«
Uporabniki 🔍	✓ Core Release
Povzetek 🏾	
Posodobitve Izhod	✓ Nonfree Release
N	▶ Pomoč Nagrej

Here you have the list of available repositories. Not all repositories are available, according to which media you use for installing. The repositories selection determines which packages will be available for selection during the next steps.

- The Core repository cannot be disabled as it contains the base of the distribution.
- The Nonfree repository includes packages that are free-of-charge, i.e. Mageia may redistribute them, but they contain closed-source software (hence the name Non-free). For example this repository includes nVidia and AMD graphics card proprietary drivers, firmware for various WiFi cards, etc.
- The Tainted repository includes packages released under a free license. The main criteria for placing packages in this repository is that they may infringe patents and copyright laws in some countries, e.g. multimedia codecs needed to play various audio/video files; packages needed to play commercial video DVD's, etc.

### 3.7.2. Izbira namizja

Some choices made here will open other screens with related options.

After the selection step(s), you will see a slideshow during the installation of required packages. The slideshow can be disabled by pressing the Details button.

Ö mageia	IZBIRA NAMIZJA	
NAMESTITEV Jezik • Licenca • Razdelitev diska Nameščanje NASTAVITEV Uporabniki Povzetek • Posodobitve Izhod	tu lahko izberete namizno okolje, ki bo nameščeno. Kliknite na sliko, da vidite ce ci predogled	
	▶ Pomoč Naprej	J

- Choose whether you prefer to use the KDE Plasma or GNOME desktop environment. Both come with a full set of useful applications and tools.
- Select Custom if you do not wish to use either (or, actually use both) of these, or if you want to modify the default software choices for these desktop environments. The LXDE desktop, for instance, is lighter than the previous two, sporting less eye candy and having fewer packages installed by default.

### 3.7.3. Izbira skupin paketov

A							
Omageia	IZBIRA SKUPIN PAKETOV						
	• Delovna postaja						
	🗸 Internetna postaja	📃 Omrežni računalnik (odjemalec)					
NAMESTITEV	🗸 Nastavitev	🗸 Konzolna orodja					
Jezik ● Licenca ●	📃 Razvoj	📃 Dokumentacija					
Razdelitev diska 🤍	• Strežnik						
Nameščanje 🔍	Splet/FTP	🗌 Pošta					
NASTAVITEV	📃 Požarni zid/usmerjevalnik	🔵 Omrežni računalnik (strežnik)					
Uporabniki Povzetek	• Grafično okolje						
Posodobitve •	Delovna postaja XFCE						
Izhod 🔍							
1		•					
4	📃 Izbira posamičnih paketov						
- An	Skupna velikost: 1196 / 2802 MB						
	▶ Pomoč	Odstrani izbiro Naprej					

Packages are arranged into common groups, to make choosing what you need on your system a lot easier. The groups are fairly self explanatory, however more information about the content of each is available in tool-tips which become visible as the mouse is hovered over them.

- Delovna postaja
- Strežnik
- Grafično okolje
- Individual Package Selection: you can use this option to manually add or remove packages

See  $\underline{\text{Minimal Install}}$  for instructions on how to do a minimal install (without or with X & IceWM).

### 3.7.4. Minimalna namestitev

Minimal Installation is intended for those with specific uses in mind for Mageia, such as a server or a specialised workstation. You will probably use this option combined with the Individual package selection option to fine-tune your installation. See <u>Choose</u> <u>Packages Tree</u>.

• You can choose a Minimal Installation by de-selecting everything in the Package Group Selection screen, see <u>Choose Package Groups</u>. If desired, you can additionally tick the Individual package selection option in the same screen.

• If you choose this installation method, then the relevant screen (see screenshot below) will offer you a few useful extras to install, such as documentation and "X".

If the With X option is selected, then IceWM (a lightweight desktop environment) will also be included.

The basic documentation is provided in the form of "man" and "info" pages. It contains the man pages from the <u>Linux Documentation Project</u> [http://www.tldp.org/manpages/man.html] and the <u>GNU coreutils</u> [http://www.gnu.org/software/coreutils/manual/] info pages.

A	
Omageia	VRSTA NAMESTITVE
	Z grafičnim okoljem     ✓ Namesti predlagane pakete
NAMESTITEV Jezik ●	✓ Z osnovno dokumentacijo (priporočeno)
Licenca • Razdelitev diska •	Zares najmanjša možna namestitev (še posebej brez urpmi)
Nameščanje 🔍	
NASTAVITEV Uporabniki	
Povzetek 🍳	
Posodobitve ● Izhod ●	
6	
× -	▶ Pomoč Nazaj Naprej

3.7.5. Izbira posamičnih paketov

۸							
Ömageia	UPRAVLJANJE S PROGRAMI						
	Izberite pakete, ki jih želite namestiti						
	>-Strežnik			Ô			
NAMESTITEV	>-Grafično okolje						
Jezik 🔍	🗸 Delovna postaja	$\checkmark$					
Licenca •	<ul> <li>Internetna postaja</li> </ul>	$\checkmark$					
Razdelitev diska 🔍	bind-util						
Nameščanje 🔍	— firefox	$\checkmark$					
NASTAVITEV	- firefox-en_GB	$\checkmark$					
Uporabniki 🍳	– lftp			$\sim$			
Povzetek Posodobitve		Informacije					
Izhod	Ime: bind-utils Različica: 9.9.4.P2-1.mga4 Velikost: 9010 KB Pomembnost: pomembno			<u></u>			
4	✓ Prikaži samodejno izbrane	Skupna velikost: 1225 / 280 e pakete	1 MB				
× -	🗈 Pomoč 🛛 🕎		Nazaj	Namesti			

Here you can add or remove any extra packages to customize your installation.

After having made your choice, you can click on the floppy icon at the bottom of the page to save your choice of packages (saving to a USB key works, too). You can then use this file to install the same packages on another system, by pressing the same button during install and choosing to load it.

# **3.8. User Management**

2				
Ömageia				
	• Nastavite geslo skrbnika (uporabnik			
	Geslo	•••••••		
NAMESTITEV	Geslo (ponovno)			
Jezik ● Licenca ●	• Dodajte uporabnika			
Razdelitev diska 🔍		•		
Nameščanje 🔍	Ikona	<b>Č</b>		
NASTAVITEV	Pravo ime			
Uporabniki 🤍	lme za prijavo	<b>v</b>		
Povzetek 🍳	Geslo			
Posodobit∨e ● Izhod ●	Geslo (ponovno)			
izhoù -				
	▶ Napredno			
1				
6				
. An				
	▶ Pomoč	Narkej		
- BA				

# 3.8.1. Nastavite geslo skrbnika (uporabnika root):

It is advisable for all Mageia installations to set a superuser (Administrator) password, usually called the root password in Linux. As you type a password into the top box a shield will change from red-to-yellow-to-green depending on the strength of the password. A green shield shows you are using a strong password. You need to repeat the same password in the box underneath, to check that the first entry was not mistyped.



All passwords are case-sensitive. It is best to use a mixture of letters (upper and lower case), numbers and other characters in a password.

# 3.8.2. Dodajte uporabnika

Add a User here. A regular user has fewer privileges than the superuser (root), but enough to use the Internet, office applications or play games and anything else the average user might use a computer for.

• Icon

Click on this button if you want to change the user's icon

#### • Real Name

Insert the user's real name into this text box

### • Login Name

Enter the user login name or let DrakX use a version of the user's real name. **The login name is case-sensitive.** 

### Password

Type in the user password. There is a shield at the end of the text box that indicates the strength of the password. (See also <u>Opomba</u>)

**Password (again):** Retype the user password. DrakX will check that you have not mistyped the password.



Any users added while installing Mageia, will have a home directory that is both read and write protected (umask=0027)

Več uporabnikov je med namestitvijo možno dodati v koraku Nastavitve - povzetek. Izberite Upravljanje uporabnikov.

Dovoljenje dostopa lahko spremenite tudi po namestitvi

### **3.8.3. User Management (advanced)**

The Advanced option allows you to edit further settings for the user you are adding.

- Shell: This drop-down list allows you to change the shell available to any user you added in the previous screen. Options are Bash, Dash and Sh
- User ID: Here you can set the user ID for any user you added in the previous screen. If you are unsure what the purpose of this is, then leave it blank.
- Group ID: This lets you set the group ID. Again, if unsure, leave it blank.

# **3.9. Graphical Configuration**

# 3.9.1. Nastavitev grafične kartice in monitorja

Å				
Ömageia	NASTAVITEV GRAFIČNE KARTICE IN ZASLONA			
	Grafična kartica	Intel 810 and later		
	Zaslon	Po meri		
NAMESTITEV Jezik ●	Ločljivost	Samodejno		
Licenca 🔍		Možnosti		
Razdelitev diska •				
Nameščanje 单				
NASTAVITEV				
Uporabniki •				
Povzetek 🏻				
Posodobitve 🍳				
Izhod 🔍				
		▶		
- <u>1</u>				
. 🙆				
NI -	🕨 Pomoč	Naprej		
50				

No matter which graphical environment (also known as desktop environment) you chose for this install of Mageia, they are all based on a graphical user interface system called X Window System, or simply "X". So in order for KDE Plasma, GNOME, LXDE or any other graphical environment to work well, the following "X" settings need to be correct.

Choose the appropriate settings manually if you think the details are incorrect, or if none are shown.

### • Graphic Card

If you need to, you can select a specific card from this expandable list. See <u>Razde-lek 3.9.2</u>, "Izberite strežnik X ()nastavite grafično kartico".

### • Monitor

You can choose Plug 'n Play, if applicable, or choose your monitor from the Vendor or Generic lists. Choose Custom if you prefer to manually set the horizontal and vertical refresh rates of your monitor. See <u>Razdelek 3.9.3</u>, "Izberite vaš zaslon".

#### • Resolution

The resolution and color depth of your monitor can be set here.

• Test

The test button does not always appear during install. If the option is there, and you test your settings, you should be asked to confirm that your settings are correct. If you answer Yes, the settings will be kept. If you don't see anything, you'll return to the configuration screen and be able to reconfigure everything until the test result is satisfactory. If the test option is not available, then make sure your settings are on the safe side.

#### • Options

Here you can choose to enable or disable various options.



There is a risk of damaging a monitor if you choose refresh rates that are outside the frequency range of that monitor. This applies to older CRT displays: modern monitors will reject an unsupported frequency and normally enter standby mode.

## 3.9.2. Izberite strežnik X ()nastavite grafično kartico

Å				
Ömageia	GRAFIČNI STREŽNIK			
	Izberite grafični strežnik			
NAMESTITEV	-Vendor			
Jezik ● Licenca ●	>- 3Dlabs			
Licenca ● Razdelitev diska ●	>- ATI			
Nameščanje •	>- Ark Logic			
	>- Chips & Technologies			
NASTAVITEV	>- Cirrus Logic			
Uporabniki •	>- Diamond			
Povzetek • Posodobitve •	>- Digital			
Izhod	v- Intel			
iznou s	– 740-based cards			
	810 and later			
	– Poulsbo US15W (GMA500)			
	Vermilion-based cards			
>- Matrox				
in the second se				
	▶ Pomoč Nazaj Naprej			
		_		
202				

DrakX has a very comprehensive database of video cards and will usually correctly identify your video device.

If the installer has not correctly detected your graphic card and you know which one you have, you can select it from the tree by:

- Vendor
- then the make of your card

• and the model of card

If you cannot find your card in the vendor lists (because it's not yet in the database or it's an older card) you may find a suitable driver in the Xorg category, which provides more than 40 generic and open source video card drivers. If you still can't find a specific driver for your card there is the option of using the VESA driver which provides basic capabilities.



Be aware that if you select an incompatible driver you may only have access to the Command Line Interface

Some video card manufacturers provide proprietary drivers for Linux which may only be available in the Nonfree repository and in some cases only from the card manufacturers' websites. The Nonfree repository needs to be explicitly enabled to access them. If you didn't enable it previously, you should do this after your first reboot.

## 3.9.3. Izberite vaš zaslon

DrakX has a very comprehensive database of monitors and will usually correctly identify yours.



Selecting a monitor with different characteristics could damage your monitor or video hardware. Please don't try something without knowing what you are doing. If in doubt you should consult your monitor documentation.

Ömageia	ZASLON
<b>NAMESTITEV</b> Jezik • Licenca • Razdelitev diska • Nameščanje • <b>NASTAVITEV</b> Uporabniki • Povzetek •	Izberite zaslon Po meri Plug'n Play ()  - Proizvajalec  - Aamazing Aamazing CM-8426 Aamazing MS-8431 - Acer
Posodobitve • Izhod •	<ul> <li>Action Systems, Inc.</li> <li>Actix</li> <li>Adara</li> <li>ADI</li> <li>Amptron International,Inc.</li> <li>AOC</li> <li>Apollo</li> <li>Pomoč</li> <li>Nazaj</li> <li>Naprej</li> </ul>

Custom This option allows you to set two critical parameters: the vertical refresh rate and the horizontal sync rate. Vertical refresh determines how often the screen is refreshed and horizontal sync is the rate at which scan lines are displayed.

> It is VERY IMPORTANT that you do not specify a monitor type with a sync range that is beyond the capabilities of your monitor: you may damage your monitor. If in doubt, choose a conservative setting and consult your monitor documentation.

Plug'n Play This is the default option and automatically tries to determine the monitor type from the monitor database.

Vendor If the installer has not correctly detected your monitor and you know which one you have, you can select it from the tree by selecting:

- Manufacturer
- Monitor model
- Generic Selecting this group will list nearly 30 display configurations such as 1024x768 @ 60Hz and includes flat-panel displays as used in laptops. This is often a good monitor selection group if you need to use the VESA card driver when your video hardware cannot be determined automatically. Once again it may be wise to be conservative in your selections.

# **3.10. Bootloader**

## 3.10.1. Grub2

Grub2 on Legacy MBR/GPT systems

- GRUB2 (with or without graphical menu) will be used exclusively as the bootloader for a Legacy/MBR or Legacy/GPT system.
- By default, a new bootloader will be written into either the MBR (Master Boot Record) of your first hard drive or in the BIOS boot partition.

## Grub2-efi on UEFI systems

- GRUB2-efi will be used exclusively as the bootloader for a UEFI system.
- By default, a new bootloader (Grub2-efi) will be written into the ESP (EFI System Partition).

If there are already UEFI-based operating systems installed on your computer (Windows 8 for example), the Mageia installer will detect the existing ESP created by Windows and add grub2-efi to it. If no ESP exists, then one will be created. Although it is possible to have several ESPs, only one is required, whatever the number of operating systems you have.

# **3.10.2. Bootloader Setup**

3.10.2.1. Glavne možnosti zagonskega nalagalnika

Ömageja	GLAVNE MOŽNOSTI ZAGONSKEGA NALAGALN	IKA
	<ul> <li>Zagonski nalagalnik</li> <li>Kateri zagonski nalagalnik želite uporabiti?</li> <li>Zagonska naprava</li> </ul>	GRUB v grafičnem načinu 🗸
NAMESTITEV Jezik ● Licenca ●	• Glavne nastavitve	/dev/sda (Toshiba MK4026GA) V
Razdelitev diska ● Nameščanje ●	Premor pred zaganjanjem privzete slike	10
NASTAVITEV Uporabniki • Povzetek •	Geslo Geslo (ponovno)	
Posodobitve Izhod	▶ Napredno	
1		
	▶ Pomoč	Nazaj Naprej

## Bootloader to use

This feature is only available to Legacy MBR/BIOS systems. Users of UEFI systems will not see this option here.

### • Boot device

Don't change this unless you really know what you are doing

## Delay before booting the default image

This text box lets you set a delay, in seconds, before the default operating system is started up.

### • Security

This allows you to set a password for the bootloader. This means a username and password will be required when booting in order to select a booting entry or change settings. This is optional, and most people are not likely to have a need for it. The username is root and the password is the one chosen hereafter.

### Password

Choose a password for the bootloader (optional)

### • Password (again)

Retype the password and DrakX will check that it matches with the one set above

### Advanced

• Enable ACPI

ACPI (Advanced Configuration and Power Interface) is a standard for power management. It can save energy by stopping unused devices. Deselecting it could be useful if, for example, your computer does not support ACPI or if you think the ACPI implementation might cause some problems (for instance random reboots or system lockups).

• Enable SMP

This option enables/disables symmetric multiprocessing for multi-core processors

• Enable APIC

Enabling this gives the operating system access to the Advanced Programmable Interrupt Controller. APIC devices permit more complex priority models, and Advanced IRQ (Interrupt Request) management.

• Enable Local APIC

Here you can set Local APIC, which manages all external interrupts for a specific processor in an SMP system

## **3.10.2.2. Bootloader Configuration**

Omageia	BOOTLOADE	R CONFIGURATION
Mageia 6	Default Append	Mageia splash quiet noiswmd resume=UUID=6006f83f-e9d6-49d4-8bd2-bdbec
INSTALLATION Language • License • Partitioning •	Probe	Foreign OS
Installing •	▶ Advanced	
Users • Summary • Updates •		
Exit		
	🕨 Help	Previous Next

#### • Default

The operating system to be started up by default.

## Append

This option lets you pass information to the kernel or tell the kernel to give you more information as it boots.

#### Probe foreign OS

If you already have other operating systems installed, Mageia attempts to add them to your new Mageia boot menu. If you don't want this behaviour, then untick the Probe Foreign OS option.

Advanced


Ömaç		OTLOADER CONF	IGURATION			1
Mageia 6 INSTALI Lang Lic Partiti Inst CONFIGUE Sum Up	Video mode	h ESP or MBR			•	4-8bd2-bdbe¢
				Cancel	Ok	Next
						~

• Video mode

This sets the screen size and colour depth to be used by the boot menu. If you click the down-triangle you will be offered other size and colour depth options.

• Do not touch ESP or MBR

Select this option if you don't want a bootable Mageia, but would rather chain-load it from another OS. You will get a warning that the bootloader is missing. Click Ok if you are sure you understand the implications, and wish to proceed.



## **3.10.3. Other Options**

#### 3.10.3.1. Uporaba obstoječega zagonskega nalagalnika

The exact procedure for adding Mageia to an existing bootloader is beyond the scope of this documentation. However in most cases it will involve running the relevant bootloader installation program, which should detect Mageia and automatically add an entry for it in the bootloader menu. See the documentation for the relevant operating system.

**3.10.3.2. Installing Without a Bootloader** 

While you can opt to install Mageia without a bootloader (see section 2.1 Advanced), this is not recommended unless you absolutely know what you are doing, as without some form of bootloader your operating system will be unable to start.

**3.10.3.3. Add or Modify a Boot Menu Entry** 

To do this you need to manually edit /boot/grub2/custom.cfg or use the software **grub-customizer** tool instead (available in the Mageia repositories).



For more information, see: <u>https://wiki.mageia.org/en/Grub2-efi_and_Mageia</u>

# **3.11. Configuration Summary**

A			
() mageia	SUMMARY		
Mageia 6			
	System		
INSTALLATION		Timezone - Europe/London	Configure
Language •		Country / Posion United Kingdom	Configure
License ● Partitioning ●		Country / Region - United Kingdom	Conligure
Installing •		Bootloader - grub2-graphic on /dev/sda	Configure
CONFIGURATION		User management	Configure
Users •		Services - 22 activated for 29 registered	Configure
Summary • Updates •		-	
Exit •	• Hardware		
		Keyboard - UK keyboard	Configure
		Reyboard - OK Reyboard	configure
		Mouse - Universal Any PS/2 & USB mice	Configure
	▶ Help		Next

DrakX presents a proposal for the configuration of your system depending on the choices you made and on the hardware detected. You can check the settings here and change them if you want by pressing Configure.



- Splošno pravilo je, da je najbolje sprejeti privzete vrednosti, razen v primerih:
- s privzetimi vrednostmi je nekaj že znanih težav,
- privzete vrednosti niso dale želenega rezultata ali
- some other factor mentioned in the detailed sections below is an issue

### 3.11.1. Sistemske nastavitve

#### • Timezone

DrakX selects a timezone for you, depending on your preferred language. You can change it if needed. See also <u>Configure Timezone</u>

#### Country / Region

If the selected country is wrong, it is very important that you correct the setting. See <u>Select Country</u>

#### • Bootloader

DrakX proposal for the bootloader setting

Do not change anything, unless you know how to configure GRUB2. For more information, see <u>Bootloader</u>

#### User management

You can add extra users here. They will each be allocated their own /home directories.

#### • Services

System services refer to those small programs which run in the background (daemons). This tool allows you to enable or disable certain processes.

You should check carefully before changing anything here - a mistake may prevent your computer from operating correctly. For more information, see <u>Configure Services</u>

### 3.11.2. Strojne nastavitve

### Keyboard

Configure your keyboard layout according to your location, language and type of keyboard.



If you notice a wrong keyboard layout and want to change it, keep in mind that your passwords are going to change too.

#### Mouse

Here you can add or configure other pointing devices, tablets, trackballs etc.

• Sound card

The installer will use the default driver if one is available.

If there is no actual default driver for your sound card, there may be other possible alternative drivers available to choose from. If this is the case, but you think the installer has not made the most appropriate choice, you can click on Advanced to manually specify a driver.

#### • Graphical interface

This section allows you to configure your graphics card(s) and displays. For more information, see <u>Razdelek 3.9.1</u>, "<u>Nastavitev grafične kartice in monitorja</u>"

Ömageja	POVZETEK	
• .		
	Tipkovnica - Nizozemska	Nastavitev
	Miška - Univerzalna Katerakoli miška PS/2 ali USB	Nastavitev
NAMESTITEV Jezik ●	Zvočna kartica - Intel 82801AA,82901AB,i810,i820,i830,i840,i845,MX440; SiS 7012; Ali 5455	Nastavitev
Licenca ● Razdelitev diska ●	Grafična kartica - Samodejno	Nastavitev
Nameščanje ● <b>NASTAVITEV</b> Uporabniki ●	• Omrežje in internet	
Povzetek 🏻 🤇	Omrežje - ethernet	Nastavitev
Posodobitve Izhod	Posredniški strežniki - ni nastavljeno	Nastavitev
	• Varnost	
1	Stopnja varnosti - Standardna	Nastavitev
4	Požarni zid - aktivirano	Nastavitev ^
×	▶ Pomoč	Naprej

## 3.11.3. Nastavitve omrežja in interneta

#### Network

You can configure your network here, but for network cards with non-free drivers it is better to do that after reboot, using the Mageia Control Center, if you have not yet enabled the Nonfree media repositories.



When you add a network card, do not forget to set your firewall to monitor that interface as well.

#### Proxies

A Proxy Server acts as an intermediary between your computer and the wider Internet. This section allows you to configure your computer to utilize a proxy service.

You may need to consult your systems administrator to obtain the parameters you need to enter here.

## 3.11.4. Varnost

#### • Security Level

The Security level for your computer, in most cases the default setting (Standard) is adequate for general use. Select the option which best suits your usage.

#### • Firewall

The firewall allows you to manage which network connections are allowed on your computer. The safe and secure default is to allow ZERO inbound connections. This does not stop you connecting outbound and using your computer normally.

Please be aware that the Internet is a high risk network where there are continuous attempts to probe and attack systems. Even seemingly "safe" connections such as ICMP (for ping) have been used as covert data channels for exfiltrating data by malicious persons.

For more information, see Firewall.



Bear in mind that allowing everything (no firewall) may be very risky.

# **3.12. Locale**

# 3.12.1. Nastavite vaš časovni pas

8	
Ömageia	ČASOVNI PAS
	Izberite vaš časovni pas:
NAMESTITEV	
Jezik •	-Isle_of_Man
Licenca ● Razdelitev diska ●	– Istanbul
Razdelitev diska ● Nameščanje ●	Jersey
Namescanje 👻	– Kaliningrad
NASTAVITEV	- Kiev
Uporabniki 🔍	– Lisbon
Povzetek 🏻 🤇	Ljubljana
Posodobitve 🔍	– London
Izhod 🍨 🗌	– Luxembourg
	– Madrid
	– Malta
1	– Mariehamn
	- Minsk
l l	V Monaca V
_ <b>@</b>	
	Nazaj Naprej

• Choose your timezone by choosing your country, or a city close to you in the same timezone.

In the next screen you can choose to set your hardware clock to local time or to GMT, also known as UTC.



If you have more than one operating system on your computer, make sure they are all set to local time, or all to UTC/GMT.

# 3.12.2. Izbor države/regije

A	
Ömageia	DRŽAVA
	Izberite državo:
NAMESTITEV	
Jezik ●	Sierra Leone
Licenca ● Razdelitev diska ●	Singapur
Nameščanje •	Sirija
Namescanje -	Slonokoščena obala
NASTAVITEV	Slovaška
Uporabniki 🔍	Slovenija
Povzetek 🏻 🧹	Somalija
Posodobitve 🔍	Srbija in Črna gora
Izhod 🄍	Srednjeafriška republika
	St. Kitts - Nevis
	Sudan
1	×
- -	▶ Napredno
N	Demoč Nazaj Naprej

- Select your country or region. This is important for all kinds of settings, like the currency and wireless regulatory domain. Setting the wrong country can lead to being unable to use a Wireless network.
- If your country isn't in the list, click the Other Countries option and choose your country / region there.



If your country is only in the Other Countries list, after clicking OK it may seem that a country from the main list was chosen. Despite this, DrakX will actually apply your choice.

### 3.12.2.1. Način vnosa

In the Other Countries screen you can also select an input method (at the bottom of the list). Input methods allow users to input multilingual characters (Chinese, Japanese, Korean, etc). IBus is the default input method, so users should not need to configure it manually. Other input methods (SCIM, GCIN, HIME, etc) also provide similar functions and can be installed if you added HTTP/FTP media before package selection.



If you missed the input method setup during installation, you can access it post-install via Configure your Computer  $\rightarrow$  System, or by running **locale-drake** as root.

# 3.13. Nastavite vaše storitve

A				
Ömageia	STORITVE			
	Izberite, katere storitve	naj se samodejno zaženejo ol	o zagonu računalnika	
	>-Drugo			
NAMESTITEV	>-Sistem			
Jezik 🔍	>-Internet	$\checkmark$		
Licenca •	✓-Omrežje	$\checkmark$		
Razdelitev diska •	– network	$\checkmark$		
Nameščanje 🔍	netvork-auth			
NASTAVITEV	– network-up	$\checkmark$		
Uporabniki •	- resolvconf			
Povzetek 🏻				
Posodobitve 🔍				
Izhod 🔍		Informacije		
	Če je omogočeno, zaht	eva deluioče omrežie		
	, ,			
1				
4				
1. L.	12 aktiviranih od 18 registriranih			
1. Y	N Damaš		Nanai	
	▶ Pomoč		Nazaj Naprej	

Tukaj lahko izberete ter nastavite storitve, ki naj se samodejno zaženejo ob zagonu računalnika.

- Click on a triangle to expand a group to all the relevant services. The settings DrakX chose are usually good.
- If you highlight a service, some information about it is shown in the info box below.

Only change things when you know very well what you are doing.

# 3.14. Izberite miško

A		
Ömageia	IZBIRA MIŠKE	
	Izberite vrsto svoje miške	
NAMESTITEV		
Jezik 单	>-PS/2	
Licenca •	>-USB	
Razdelitev diska ●	v-Univerzalna	
Nameščanje 🔍	– Katerakoli miška PS/2 ali USB – Vsili splošni vmesnik za vhodne naprave (evdev)	
NASTAVITEV	>-brez	
Uporabniki 🔍	>-busmouse	
Povzetek 🍳	>-serijska	
Posodobitve ● Izhod ●		
ichoù s		
		•
<u> </u>		
	▶ Pomoč	Nazaj Naprej

If you are not happy with how your mouse responds, you can select a different one here.

Usually, Universal  $\rightarrow$  Any PS/2 and USB mice is a good choice.

Select Universal  $\rightarrow$  Force evdev to configure the buttons that do not work on a mouse with six or more buttons.

# 3.15. Nastavitve zvoka

A	
Ömageia	NASTAVITVE ZVOČNEGA SISTEMA
NAMESTITEV	Intel Corporation 82801DB/DBL/DBM (ICH4/ICH4-L/ICH4-M) AC'97 Audio Controller Vaša kartica trenutno uporablja gonilnik ALSA »snd_intel8x0« (privzeti gonilnik za vašo kartico je »snd_intel8x0«)
Jezik ● Licenca ●	✓ Omogoči PulseAudio
Razdelite∨ diska ● Nameščanje ●	🗌 Uporabi način brez napak
NASTAVITEV Uporabniki ●	▶ Napredno
Povzetek • Posodobitve •	
Izhod 🔹	
1	
<u>\$</u>	
N -	▶ Pomoč Nazaj Naprej

This screen shows the details of the sound card driver chosen for you by the installer, and this driver should work without problems.

However, if you encounter any issues post-install, then run **draksound** or start this tool via Mageia Control Center  $\rightarrow$  Hardware  $\rightarrow$  Sound Configuration. Then, in the draksound or Sound Configuration screen, click on Troubleshooting to find useful advice about how to solve the problem.

## 3.15.1. Napredno

If there is no actual default driver for your sound card, there may be other possible alternative drivers available to choose from. If this is the case, but you think the installer has not made the most appropriate choice, you can click on Advanced to manually specify a driver.

# 3.16. Stopnja varnosti

8		
Omageia	VARNOST	
	<ul> <li>Izberite željeno stopnjo varnosti</li> <li>Standardna: To je normalna varnost, priporočeno za računalnike, ki bodo povezani v Internet kot odjemalci.</li> </ul>	
NAMESTITEV Jezik ● Licenca ● Razdelitev diska ●	Varno: Na tej varnostni stopnji postane uporaba sistema kot strežnika mogoča. Varnost je zdaj dovolj velika za uporabo sistema kot strežnika, s katerim se lahko povezujejo mnogi odjemalci. Opomba: če je vaš sistem na internetu le odjemalec, je priporočeno, da nastavite nižjo varnostno stopnjo.	
Nameščanje ● NASTAVITEV Uporabniki ●	• Varnostni administrator: Prijava ali e-pošta:	
Povzetek 🔍 Posodobitve 🔍		
Izhod	×	
	▶ Pomoč Nazaj Naprej	

### Please choose the desired security level

Standard is the default, and recommended setting for the average user.

Secure will create a highly protected system - for instance if the system is to be used as a public server.

#### Security Administrator

This item allows you to configure an email address to which the system will send security alert messages when it detects situations which require notification to a system administrator.

A good, and easy-to-implement, choice is to enter <user>@localhost - where <user> is the login name of the user to receive these messages.



The system sends such messages as **Unix Mailspool messages**, not as "ordinary" SMTP mail: this user must therefore be configured for receiving such mail!

It will always be possible to adjust your security settings post-install in the Security section of the Mageia Control Center.

# 3.17. Požarni zid

This section allows you to configure some simple firewall rules: they determine which type of message from the Internet will be accepted by the target system. This, in turn, allows the corresponding services on the system to be accessible from the Internet.

In the default setting (no button is checked), no service of the system is accessible from the network. The Everything (no firewall) option enables access to all services of the machine - an option that does not make much sense in the context of the installer since it would create a totally unprotected system. Its veritable use is in the context of the Mageia Control Center (which uses the same GUI layout) for temporarily disabling the entire set of firewall rules for testing and debugging purposes.

All other options are more or less self-explanatory. As an example, you will enable the CUPS server if you want printers on your machine to be accessible from the network.

### Napredno

The Advanced option opens a window where you can enable a series of services by typing a list of "couples" (blank separated)

<številka-vrat>/<protokol>

- <port-number> is the value of the port assigned to the service you want to enable (e.g. 873 for the RSYNC service) as defined in RFC-433;

- <protocol> is one of TCP or UDP - the internet protocol that is used by the service.

For instance, the entry for enabling access to the RSYNC service therefore is 873/tcp.

In case a service is implemented to use both protocols, you specify 2 couples for the same port.


# 3.18. Posodobitve

Ömageja	POSODOBITVE
NAMESTITEV Jezik • Licenca • Razdelitev diska • Nameščanje • NASTAVITEV Uporabniki • Povzetek •	Zdaj imate možnost, da s strežnika prenesete posodobljene pakete. Ti paketi so bili posodobljeni po izdaji distribucije. Zelo verjetno vsebujejo varnostne popravke in popravke napak. Za namestitev teh paketov morate imeti vzpostavljeno internetno povezavo. Ali želite namestiti posodobitve?
Posodobitve Izhod	Ne ▶ Pomoč Naprej
39	

Since this version of Mageia was released, some packages will have been updated or improved.

- Select Yes if you wish to download and install them
- Select No if you don't want to do this now, or if you aren't connected to the Internet
- Press Next to continue

# 3.19. Čestitke



You have finished installing and configuring Mageia and it is now safe to remove the installation medium and reboot your computer.

After rebooting, you can use the bootloader screen to choose which operating system to start (if there are more than one on your computer).

If you didn't adjust the settings for the bootloader, your Mageia install will be automatically selected and started.

Uživajte

Visit <u>www.mageia.org/en/</u> [http://www.mageia.org/en/] if you have any questions or want to contribute to Mageia

# 3.20. Odstrani Magejo

If Mageia didn't convince you or you can't install it correctly - in short you want get rid of it - that is your right and Mageia also gives you the possibility to uninstall. This is not true for every operating system.

After backing up your data, reboot your Mageia installation DVD and select Rescue system, then Restore Windows boot loader. At the next boot, you will only have Windows, with no option to choose your Mageia operating system.

In Windows, to recover the space used by Mageia partitions: click on Start  $\rightarrow$  Control Panel  $\rightarrow$  Administrative Tools  $\rightarrow$  Computer Management  $\rightarrow$  Storage  $\rightarrow$  Disk Management.

You will recognise a Mageia partition because they are labeled Unknown, and also by their size and place on the disk. Right-click on each of these partitions and select Delete to free up the space.

If you are using Windows XP, you can create a new partition and format it (FAT32 or NTFS). It will then get a partition letter.

If you have Vista or 7, you have one more possibility, you can extend the existing partition that is at the left of the freed space. There are other partitioning tools that can be used, such as **gparted**, available for both Windows and Linux. As always, when changing partitions, be very careful to back up anything important to you.